

System configuration

How to access and modify SPeASY.ini

For all VIOSO Software solutions there are a lot of parameters that configure how each program behaves. Usually these options are managed by VIOSO and there is no need for the user to make changes.

However, there may be situations when accessing and modifying such a parameter is required. In this case, please follow these instructions to access and modify the main configuration file "SpEASY.ini":

1. Close the VIOSO program whose main configuration you want to edit.
2. Locate the appropriate configuration file "SPeASY.ini" (see table below).
3. Make a copy in a folder where you have read&write access.
4. Open the file with a text editor (notepad or similar, do not use word processing tools like "Microsoft Word").
5. Edit the file and save. Please note, that SPeASY.ini contains XML formatted content (not "INI"-file formatted content as the file extension might indicate)
6. Copy the file back to its original location, overwriting the existing file.
7. Restart the VIOSO program and test the results.

Location of the main configuration file "SPeASY.ini" for VIOSO Calibrator (part of VIOSO Anyblend) and VIOSO Player - this influences the behaviour during the calibration or content playback:

Program	x64/x86	Location of configuration file
Anyblend Calibrator	64 Bit	C:\Program Files\VIOSO Anyblend\SPCalibrator\SPeASY.ini
	32 Bit	C:\Program Files (x86)\VIOSO Anyblend\SPCalibrator\SPeASY.ini
Anyblend VR&SIM Calibrator	64 Bit	C:\Program Files\VIOSO Anyblend VR&SIM\SPCalibrator\SPeASY.ini
	32 Bit	C:\Program Files (x86)\VIOSO Anyblend VR&SIM\SPCalibrator\SPeASY.ini
VIOSO Player	64 Bit	C:\Program Files\VIOSO Player\SPeASY.ini
	32 Bit	C:\Program Files\VIOSO Player (x86)\SPeASY.ini

System configuration

Location of the main configuration file "SPeASY.ini" for VIOSO Anblend (main program part) - this influences how warping & blending is applied to GPUs or operating system:

Program	x64/x86	Location of configuration file
Anyblend	64 Bit	C:\Program Files\VIOSO Anyblend\SPeASY.ini
	32 Bit	C:\Program Files (x86)\VIOSO Anyblend\SPeASY.ini
Anyblend VR&SIM	64 Bit	C:\Program Files\VIOSO Anyblend VR&SIM\SPeASY.ini
	32 Bit	C:\Program Files (x86)\VIOSO Anyblend VR&SIM\SPeASY.in

Unique solution ID: #1053

Author: Emanuel Züger

Last update: 2017-01-23 10:36